CS162
Operating Systems and Systems Programming
Lecture 5

Introduction to Networking (Finished), Concurrency (Processes and Threads)

February 4th, 2015

Prof. John Kubiatowicz

http://cs162.eecs.Berkeley.edu

Recall: Namespaces for communication over IP

- Hostname
  - www.eecs.berkeley.edu
- IP address
  - 128.32.244.172 (ipv6?)
- Port Number
  - 0-1023 are "well known" or "system" ports
    - » Superuser privileges to bind to one
  - 1024 – 49151 are "registered" ports (registry)
    - » Assigned by IANA for specific services
  - 49152–65535 ($2^{15}+2^{14}$ to $2^{16}-1$) are "dynamic" or "private"
    - » Automatically allocated as "ephemeral Ports"

Recall: Use of Sockets in TCP

- Socket: an abstraction of a network I/O queue
  - Embodies one side of a communication channel
    - » Same interface regardless of location of other end
    - » Could be local machine (called "UNIX socket") or remote machine (called "network socket")
  - First introduced in 4.2 BSD UNIX: big innovation at time
    - » Now most operating systems provide some notion of socket
- Using Sockets for Client-Server (C/C++ interface):
  - On server: set up "server-socket"
    - » Create socket, Bind to protocol (TCP), local address, port
    - » Call listen(): tells server socket to accept incoming requests
    - » Perform multiple accept() calls on socket to accept incoming connection request
    - » Each successful accept() returns a new socket for a new connection; can pass this off to handler thread
  - On client:
    - » Create socket, Bind to protocol (TCP), remote address, port
    - » Perform connect() on socket to make connection
    - » If connect() successful, have socket connected to server

Recall: Socket Setup over TCP/IP



- Server Socket: Listens for new connections
  - Produces new sockets for each unique connection
- Things to remember:
  - Connection involves 5 values: [Client Addr, Client Port, Server Addr, Server Port, Protocol]
  - Often, Client Port "randomly" assigned
    - » Done by OS during client socket setup
  - Server Port often "well known"
    - » 80 (web), 443 (secure web), 25 (sendmail), etc
    - » Well-known ports from 0—1023

Example: Server Protection and Parallelism



Recall: Server Protocol (v3)

```
while (1) {
    listen(lstnsockfd, MAXQUEUE);
    consockfd = accept(lstnsockfd, (struct sockaddr *) &cli_addr,
                                                   &clilen);
    cpid = fork();              /* new process for connection */
    if (cpid > 0) {             /* parent process */
      close(consockfd);
    } else if (cpid == 0) {      /* child process */
      close(lstnsockfd);        /* let go of listen socket */

      server(consockfd);

      close(consockfd);
      exit(EXIT_SUCCESS);         /* exit child normally */
    }
  }
close(lstnsockfd);
```


Server Address - itself

```
memset((char *) &serv_addr,0, sizeof(serv_addr));
serv_addr.sin_family      = AF_INET;
serv_addr.sin_addr.s_addr = INADDR_ANY;
serv_addr.sin_port        = htons(portno);
```

- Simple form
- Internet Protocol
- accepting any connections on the specified port
- In "network byte ordering"

Client: getting the server address

```
struct hostent *buildServerAddr(struct sockaddr_in *serv_addr,
                                char *hostname, int portno) {
  struct hostent *server;

  /* Get host entry associated with a hostname or IP address */
  server = gethostbyname(hostname);
  if (server == NULL) {
    fprintf(stderr,"ERROR, no such host\n");
    exit(1);
  }

  /* Construct an address for remote server */
  memset((char *) serv_addr, 0, sizeof(struct sockaddr_in));
  serv_addr->sin_family = AF_INET;
  bcopy((char *)server->h_addr,
        (char *)&(serv_addr->sin_addr.s_addr), server->h_length);
  serv_addr->sin_port = htons(portno);

return server;
}
```

BIG OS Concepts so far

- Processes
- Address Space
- Protection
- Dual Mode
- Interrupt handlers (including syscall and trap)
- File System
  - Integrates processes, users, cwd, protection
- Key Layers: OS Lib, Syscall, Subsystem, Driver
  - User handler on OS descriptors
- Process control
  - fork, wait, signal, exec
- Communication through sockets
- Client-Server Protocol

Course Structure: Spiral



Recall: Traditional UNIX Process

- Process: Operating system abstraction to represent what is needed to run a single program
  - Often called a "HeavyWeight Process"
  - No concurrency in a "HeavyWeight Process"
- Two parts:
  - Sequential program execution stream
    - » Code executed as a sequential stream of execution (i.e., thread)
    - » Includes State of CPU registers
  - Protected resources:
    - » Main memory state (contents of Address Space)
    - » I/O state (i.e. file descriptors)

How do we Multiplex Processes?

- The current state of process held in a process control block (PCB):
  - This is a "snapshot" of the execution and protection environment
  - Only one PCB active at a time
- Give out CPU time to different processes (Scheduling):
  - Only one process "running" at a time
  - Give more time to important processes
- Give pieces of resources to different processes (Protection):
  - Controlled access to non-CPU resources
  - Example mechanisms:
    - » Memory Mapping: Give each process their own address space
    - » Kernel/User duality: Arbitrary multiplexing of I/O through system calls



Process Control Block

CPU Switch From Process to Process



- This is also called a "context switch"
- Code executed in kernel above is overhead
  - Overhead sets minimum practical switching time
  - Less overhead with SMT/hyperthreading, but… contention for resources instead

Lifecycle of a Process



- As a process executes, it changes state:
  - new: The process is being created
  - ready: The process is waiting to run
  - running: Instructions are being executed
  - waiting: Process waiting for some event to occur
  - terminated: The process has finished execution

Process Scheduling



- PCBs move from queue to queue as they change state
  - Decisions about which order to remove from queues are Scheduling decisions
  - Many algorithms possible (few weeks from now)

Ready Queue And Various I/O Device Queues

- Thread not running ⇒ TCB is in some scheduler queue
  - Separate queue for each device/signal/condition
  - Each queue can have a different scheduler policy



Administrivia

- Group signups: 4 members/group
  - Link posted by Friday
  - Groups need to be finished by Monday!
  - Form asks which section you attend
- Moving section #109
  - From Friday 10-11 (3102 Etcheverry) ⇒ Thursday 12-1 (320 Soda)
  - There is still a Friday 10-11 in 3111 Etcheverry
- Conflicts for Final: Please let me know this week!
- Need to get to know your Tas
  - Consider moving out of really big sections!
- Finding info on your own is a good idea!
  - Learn your tools, like "man"
  - Can even type "man xxx" into google!
    - » Example: "man ls"

Modern Process with Threads

- Thread: *a sequential execution stream within process* (Sometimes called a "Lightweight process")
  - Process still contains a single Address Space
  - No protection between threads
- Multithreading: *a single program made up of a number of different concurrent activities*
  - Sometimes called multitasking, as in Ada …
- Why separate the concept of a thread from that of a process?
  - Discuss the "thread" part of a process (concurrency)
  - Separate from the "address space" (protection)
  - Heavyweight Process ≡ Process with one thread

Single and Multithreaded Processes



- Threads encapsulate concurrency: "Active" component
- Address spaces encapsulate protection: "Passive" part
  - Keeps buggy program from trashing the system
- Why have multiple threads per address space?

Thread State

- State shared by all threads in process/addr space
  - Content of memory (global variables, heap)
  - I/O state (file descriptors, network connections, etc)
- State "private" to each thread
  - Kept in TCB ≡ Thread Control Block
  - CPU registers (including, program counter)
  - Execution stack – what is this?
- Execution Stack
  - Parameters, temporary variables
  - Return PCs are kept while called procedures are executing

Execution Stack Example

```
A(int tmp) {
  if (tmp<2)
    B();
  printf(tmp);
}
B() {
  C();
}
C() {
  A(2);
}
A(1);
```



- Stack holds temporary results
- Permits recursive execution
- Crucial to modern languages

Motivational Example for Threads

- Imagine the following C program:

```
main() {
    ComputePI("pi.txt");
    PrintClassList("clist.text");
}
```

- What is the behavior here?
  - Program would never print out class list
  - Why? ComputePI would never finish

Use of Threads

- Version of program with Threads (loose syntax):

```
main() {
    ThreadFork(ComputePI("pi.txt"));
    ThreadFork(PrintClassList("clist.text"));
}
```

- What does "ThreadFork()" do?
  - Start independent thread running given procedure
- What is the behavior here?
  - Now, you would actually see the class list
  - This *should* behave as if there are two separate CPUs



Memory Footprint: Two-Threads

- If we stopped this program and examined it with a debugger, we would see
  - Two sets of CPU registers
  - Two sets of Stacks
- Questions:
  - How do we position stacks relative to each other?
  - What maximum size should we choose for the stacks?
  - What happens if threads violate this?
  - How might you catch violations?



Actual Thread Operations

- thread_fork(func, args)
  - Create a new thread to run func(args)
  - Pintos: thread_create
- thread_yield()
  - Relinquish processor voluntarily
  - Pintos: thread_yield
- thread_join(thread)
  - In parent, wait for forked thread to exit, then return
- thread_exit
  - Quit thread and clean up, wake up joiner if any
  - Pintos: thread_exit

- pThreads: POSIX standard for thread programming

Dispatch Loop

- Conceptually, the dispatching loop of the operating system looks as follows:

```
Loop {
   RunThread();
   ChooseNextThread();
   SaveStateOfCPU(curTCB);
   LoadStateOfCPU(newTCB);
}
```

- This is an *infinite* loop
  - One could argue that this is all that the OS does
- Should we ever exit this loop???
  - When would that be?

Running a thread

Consider first portion: `RunThread()`

- How do I run a thread?
  - Load its state (registers, PC, stack pointer) into CPU
  - Load environment (virtual memory space, etc)
  - Jump to the PC

- How does the dispatcher get control back?
  - Internal events: thread returns control voluntarily
  - External events: thread gets *preempted*

Internal Events

- Blocking on I/O
  - The act of requesting I/O implicitly yields the CPU
- Waiting on a "signal" from other thread
  - Thread asks to wait and thus yields the CPU
- Thread executes a `yield()`
  - Thread volunteers to give up CPU

```
computePI() {
   while(TRUE) {
      ComputeNextDigit();
      yield();
   }
}
```

Stack for Yielding Thread



- How do we run a new thread?

```
run_new_thread() {
    newThread = PickNewThread();
    switch(curThread, newThread);
    ThreadHouseKeeping(); /* Do any cleanup */
}
```

- How does dispatcher switch to a new thread?
  - Save anything next thread may trash: PC, regs, stack
  - Maintain isolation for each thread

What do the stacks look like?

- Consider the following code blocks:

```
proc A() {
    B();

}
proc B() {
    while(TRUE) {
        yield();
    }
}
```



- Suppose we have 2 threads:
  - Threads S and T

Saving/Restoring state (often called "Context Switch)

```
Switch(tCur,tNew) {
    /* Unload old thread */
    TCB[tCur].regs.r7 = CPU.r7;
        …
    TCB[tCur].regs.r0 = CPU.r0;
    TCB[tCur].regs.sp = CPU.sp;
    TCB[tCur].regs.retpc = CPU.retpc; /*return addr*/

    /* Load and execute new thread */
    CPU.r7 = TCB[tNew].regs.r7;
        …
    CPU.r0 = TCB[tNew].regs.r0;
    CPU.sp = TCB[tNew].regs.sp;
    CPU.retpc = TCB[tNew].regs.retpc;
    return; /* Return to CPU.retpc */
}
```


Switch Details (continued)

- What if you make a mistake in implementing switch?
  - Suppose you forget to save/restore register 4
  - Get intermittent failures depending on when context switch occurred and whether new thread uses register 4
  - System will give wrong result without warning
- Can you devise an exhaustive test to test switch code?
  - No! Too many combinations and inter-leavings
- Cautionary tail:
  - For speed, Topaz kernel saved one instruction in switch()
  - Carefully documented!
    - » Only works As long as kernel size < 1MB
  - What happened?
    - » Time passed, People forgot
    - » Later, they added features to kernel (no one removes features!)
    - » Very weird behavior started happening
  - Moral of story: Design for simplicity

Some Numbers

- Frequency of performing context switches: 10-100ms
- Context switch time in Linux: 3-4 μsecs (Current Intel i7 & E5).
  - Thread switching faster than process switching (100 ns).
  - But switching across cores about 2x more expensive than within-core switching.
- Context switch time increases sharply with the size of the working set*, and can increase 100x or more.

  * The working set is the subset of memory used by the process in a time window.
- Moral: Context switching depends mostly on cache limits and the process or thread's hunger for memory.

What happens when thread blocks on I/O?



- What happens when a thread requests a block of data from the file system?
  - User code invokes a system call
  - Read operation is initiated
  - Run new thread/switch
- Thread communication similar
  - Wait for Signal/Join
  - Networking

External Events

- What happens if thread never does any I/O, never waits, and never yields control?
  - Could the ComputePI program grab all resources and never release the processor?
    - » What if it didn't print to console?
  - Must find way that dispatcher can regain control!
- Answer: Utilize External Events
  - Interrupts: signals from hardware or software that stop the running code and jump to kernel
  - Timer: like an alarm clock that goes off every some many milliseconds
- If we make sure that external events occur frequently enough, can ensure dispatcher runs

Thread Abstraction



- Infinite number of processors
- Threads execute with variable speed
  - Programs must be designed to work with any schedule

Programmer vs. Processor View

Programmer's View	Possible Execution #1	Possible Execution #2	Possible Execution #3
.	.	.	.
.	.	.	.
.	.	.	.
x = x + 1;	x = x + 1;	x = x + 1	x = x + 1
y = y + x;	y = y + x;	....	y = y + x
z = x +5y;	z = x + 5y;	thread is suspended	....
.	.	other thread(s) run	thread is suspended
.	.	thread is resumed	other thread(s) run
.	.	....	thread is resumed
		y = y + x	....
		z = x + 5y	z = x + 5y

Possible Executions



Thread Lifecycle



Shared vs. Per-Thread State



Per Thread State (Kernel Supported Threads)

- Each Thread has a *Thread Control Block* (TCB)
  - Execution State: CPU registers, program counter (PC), pointer to stack (SP)
  - Scheduling info: state, priority, CPU time
  - Various Pointers (for implementing scheduling queues)
  - Pointer to enclosing process (PCB) – user threads
  - Etc (add stuff as you find a need)
- OS Keeps track of TCBs in "kernel memory"
  - In Array, or Linked List, or …

Multithreaded Processes

- PCB points to multiple TCBs:



- Switching threads within a block is a simple thread switch
- Switching threads across blocks requires changes to memory and I/O address tables.

Examples multithreaded programs

- Embedded systems
  - Elevators, Planes, Medical systems, Wristwatches
  - Single Program, concurrent operations
- Most modern OS kernels
  - Internally concurrent because have to deal with concurrent requests by multiple users
  - But no protection needed within kernel
- Database Servers
  - Access to shared data by many concurrent users
  - Also background utility processing must be done

Example multithreaded programs (con't)

- Network Servers
  - Concurrent requests from network
  - Again, single program, multiple concurrent operations
  - File server, Web server, and airline reservation systems
- Parallel Programming (More than one physical CPU)
  - Split program into multiple threads for parallelism
  - This is called Multiprocessing
- Some multiprocessors are actually uniprogrammed:
  - Multiple threads in one address space but one program at a time

A typical use case



Some Actual Numbers

- Many process are multi-threaded, so thread context switches may be either within-process or across-processes.



Windows Task Manager

File Options View Help

Applications | Processes | Services | Performance | Networking | Users

Image Name	PID	User Name	CPU	Memory (Private Workin...	Threads	Description
thunderbird.exe *32	5544	jfc	00	422,212 K	28	Thunderbird
firefox.exe *32	6064	jfc	00	362,048 K	49	Firefox
BCU.exe *32	4752	jfc	00	109,012 K	6	Browser Configuration Utility
dwm.exe	4036	jfc	00	105,676 K	5	Desktop Window Manager
POWERPNT.EXE	140	jfc	00	102,204 K	12	Microsoft PowerPoint
explorer.exe	1780	jfc	00	73,244 K	36	Windows Explorer
Dropbox.exe *32	3380	jfc	00	56,792 K	34	Dropbox
CameraHelperShell.exe...	4892	jfc	00	15,068 K	9	Webcam Controller
emacs.exe *32	4856	jfc	00	12,996 K	3	GNU Emacs: The extensible self-doc
FlashPlayerPlugin_11_8...	4260	jfc	00	10,820 K	12	Adobe Flash Player 11.8 r800
nvxdsync.exe	3420		00	10,192 K	10	
emacs.exe *32	2736	jfc	00	10,000 K	3	GNU Emacs: The extensible self-doc
BtvStack.exe	2708	jfc	00	9,444 K	43	Bluetooth Stack Server

Kernel Use Cases

- Thread for each user process
- Thread for sequence of steps in processing I/O
- Threads for device drivers
- …

Putting it together: Process



Putting it together: Processes



- Switch overhead: high
  - CPU state: low
  - Memory/IO state: high
- Process creation: high
- Protection
  - CPU: yes
  - Memory/IO: yes
- Sharing overhead: high (involves at least a context switch)

Putting it together: Threads



- Switch overhead: low (only CPU state)
- Thread creation: low
- Protection
  - CPU: yes
  - Memory/IO: No
- Sharing overhead: low (thread switch overhead low)

Kernel versus User-Mode threads

- We have been talking about Kernel threads
  - Native threads supported directly by the kernel
  - Every thread can run or block independently
  - One process may have several threads waiting on different things
- Downside of kernel threads: a bit expensive
  - Need to make a crossing into kernel mode to schedule
- Even lighter weight option: User Threads
  - User program provides scheduler and thread package
  - May have several user threads per kernel thread
  - User threads may be scheduled non-premptively relative to each other (only switch on yield())
  - Cheap
- Downside of user threads:
  - When one thread blocks on I/O, all threads block
  - Kernel cannot adjust scheduling among all threads
  - Option: *Scheduler Activations*
    - » Have kernel inform user level when thread blocks…

Some Threading Models

Simple One-to-One Threading Model





Many-to-One



Many-to-Many

Threads in a Process

- Threads are useful at user-level
  - Parallelism, hide I/O latency, interactivity
- Option A (early Java): user-level library, within a single-threaded process
  - Library does thread context switch
  - Kernel time slices between processes, e.g., on system call I/O
- Option B (SunOS, Unix variants): green Threads
  - User-level library does thread multiplexing
- Option C (Windows): scheduler activations
  - Kernel allocates processors to user-level library
  - Thread library implements context switch
  - System call I/O that blocks triggers upcall
- Option D (Linux, MacOS, Windows): use kernel threads
  - System calls for thread fork, join, exit (and lock, unlock,…)
  - Kernel does context switching
  - Simple, but a lot of transitions between user and kernel mode

Putting it together: Multi-Cores



- Switch overhead: low (only CPU state)
- Thread creation: low
- Protection
  - CPU: yes
  - Memory/IO: No
- Sharing overhead: low (thread switch overhead low, may not need to switch at all!)

Putting it together: Hyper-Threading



- Switch overhead between hardware-threads: very-low (done in hardware)
- Contention for ALUs/FPUs may hurt performance

Multiprocessing vs Multiprogramming

- Remember Definitions:
  - Multiprocessing ≡ Multiple CPUs
  - Multiprogramming ≡ Multiple Jobs or Processes
  - Multithreading ≡ Multiple threads per Process
- What does it mean to run two threads "concurrently"?
  - Scheduler is free to run threads in any order and interleaving: FIFO, Random, …
  - Dispatcher can choose to run each thread to completion or time-slice in big chunks or small chunks



Single and Multithreaded Processes



Supporting 1T and MT Processes



Supporting 1T and MT Processes



Correctness for systems with concurrent threads

- If dispatcher can schedule threads in any way, programs must work under all circumstances
  - Can you test for this?
  - How can you know if your program works?
- Independent Threads:
  - No state shared with other threads
  - Deterministic ⇒ Input state determines results
  - Reproducible ⇒ Can recreate Starting Conditions, I/O
  - Scheduling order doesn't matter (if `switch()` works!!!)
- Cooperating Threads:
  - Shared State between multiple threads
  - Non-deterministic
  - Non-reproducible
- Non-deterministic and Non-reproducible means that bugs can be intermittent
  - Sometimes called "Heisenbugs"

Interactions Complicate Debugging

- Is any program truly independent?
  - Every process shares the file system, OS resources, network, etc
  - Extreme example: buggy device driver causes thread A to crash "independent thread" B
- You probably don't realize how much you depend on reproducibility:
  - Example: Evil C compiler
    - » Modifies files behind your back by inserting errors into C program unless you insert debugging code
  - Example: Debugging statements can overrun stack
- Non-deterministic errors are really difficult to find
  - Example: Memory layout of kernel+user programs
    - » depends on scheduling, which depends on timer/other things
    - » Original UNIX had a bunch of non-deterministic errors
  - Example: Something which does interesting I/O
    - » User typing of letters used to help generate secure keys

Why allow cooperating threads?

- People cooperate; computers help/enhance people's lives, so computers must cooperate
  - By analogy, the non-reproducibility/non-determinism of people is a notable problem for "carefully laid plans"
- Advantage 1: Share resources
  - One computer, many users
  - One bank balance, many ATMs
    - » What if ATMs were only updated at night?
  - Embedded systems (robot control: coordinate arm & hand)
- Advantage 2: Speedup
  - Overlap I/O and computation
    - » Many different file systems do read-ahead
  - Multiprocessors – chop up program into parallel pieces
- Advantage 3: Modularity
  - More important than you might think
  - Chop large problem up into simpler pieces
    - » To compile, for instance, gcc calls cpp | cc1 | cc2 | as | ld
    - » Makes system easier to extend

High-level Example: Web Server



- Server must handle many requests
- Non-cooperating version:

```
serverLoop() {
    con = AcceptCon();
    ProcessFork(ServiceWebPage(),con);
}
```

- What are some disadvantages of this technique?

Threaded Web Server

- Now, use a single process
- Multithreaded (cooperating) version:

```
serverLoop() {
    connection = AcceptCon();
    ThreadFork(ServiceWebPage(),connection);
}
```

- Looks almost the same, but has many advantages:
  - Can share file caches kept in memory, results of CGI scripts, other things
  - Threads are *much* cheaper to create than processes, so this has a lower per-request overhead
- Question: would a user-level (say one-to-many) thread package make sense here?
  - When one request blocks on disk, all block…
- What about Denial of Service attacks or digg / Slash-dot effects?

Thread Pools

- Problem with previous version: Unbounded Threads
  - When web-site becomes too popular – throughput sinks
- Instead, allocate a bounded "pool" of worker threads, representing the maximum level of multiprogramming




```
master() {
   allocThreads(worker,queue);
   while(TRUE) {
      con=AcceptCon();
      Enqueue(queue,con);
      wakeUp(queue);
   }
}
```

```
worker(queue) {
   while(TRUE) {
      con=Dequeue(queue);
      if (con==null)
         sleepOn(queue);
      else
         ServiceWebPage(con);
   }
}
```


Classification

# threads Per AS: / # of addr spaces:	One	Many
One	MS/DOS, early Macintosh	Traditional UNIX
Many	Embedded systems (Geoworks, VxWorks, JavaOS,etc) JavaOS, Pilot(PC)	Mach, OS/2, Linux Windows 9x??? Win NT to XP, Solaris, HP-UX, OS X

- Real operating systems have either
  - One or many address spaces
  - One or many threads per address space
- Did Windows 95/98/ME have real memory protection?
  - No: Users could overwrite process tables/System DLLs

Summary

- Processes have two parts
  - Threads (Concurrency)
  - Address Spaces (Protection)
- Concurrency accomplished by multiplexing CPU Time:
  - Unloading current thread (PC, registers)
  - Loading new thread (PC, registers)
  - Such context switching may be voluntary (`yield()`, I/O operations) or involuntary (timer, other interrupts)
- Protection accomplished restricting access:
  - Memory mapping isolates processes from each other
  - Dual-mode for isolating I/O, other resources
- Various Textbooks talk about *processes*
  - When this concerns concurrency, really talking about thread portion of a process
  - When this concerns protection, talking about address space portion of a process